XPLPro

Generated by Doxygen 1.9.6

1	Class Index	1
	1.1 Class List	1
2	File Index	3
	2.1 File List	3
3	Class Documentation	5
	3.1 XPLPro Class Reference	5
	3.1.1 Detailed Description	6
	3.1.2 Constructor & Destructor Documentation	6
	3.1.2.1 XPLPro()	6
	3.1.3 Member Function Documentation	7
	3.1.3.1 begin()	7
	3.1.3.2 commandEnd()	7
	3.1.3.3 commandStart()	8
	3.1.3.4 commandTrigger() [1/2]	8
	3.1.3.5 commandTrigger() [2/2]	8
	3.1.3.6 connectionStatus()	9
	3.1.3.7 datarefReadElement()	9
	3.1.3.8 datarefReadFloat()	9
	3.1.3.9 datarefReadInt()	10
	3.1.3.10 datarefWrite() [1/6]	10
	3.1.3.11 datarefWrite() [2/6]	10
	3.1.3.12 datarefWrite() [3/6]	11
	3.1.3.13 datarefWrite() [4/6]	11
	3.1.3.14 datarefWrite() [5/6]	11
	3.1.3.15 datarefWrite() [6/6]	12
	3.1.3.16 registerCommand()	12
	3.1.3.17 registerDataRef()	12
	3.1.3.18 requestUpdates() [1/2]	13
	3.1.3.19 requestUpdates() [2/2]	13
	3.1.3.20 sendDebugMessage()	14
	3.1.3.21 sendResetRequest()	14
	3.1.3.22 sendSpeakMessage()	14
	3.1.3.23 setScaling()	15
	3.1.3.24 xloop()	15
4	File Documentation	17
	4.1 Direct inputs/main.cpp	17
	4.2 MUX inputs/main.cpp	18
	4.3 XPLPro.cpp	19
	4.4 XPLPro.h	25
	ndev .	20
m		- , u

Chapter 1

Class Index

1.1 Class List

Here are the	e classes, structs, unions and interfaces with brief descriptions:
XPLPro	
	Core class for the XPLPro Arduino library

2 Class Index

Chapter 2

File Index

2.1 File List

Here is a list of all documented files with brief descriptions:

Direct inputs/main.cpp												 								17
MUX inputs/main.cpp .									 			 								18
XPLPro.cpp									 			 								??
XPLPro.h												 								?

File Index

Chapter 3

Class Documentation

3.1 XPLPro Class Reference

Core class for the XPLPro Arduino library.

#include <XPLPro.h>

Public Member Functions

• XPLPro (Stream *device)

Constructor.

void begin (const char *devicename, void(*initFunction)(void), void(*stopFunction)(void), void(*inbound←
 Handler)(int))

Register device and set callback functions.

• int connectionStatus ()

Return connection status.

• int commandTrigger (int commandHandle)

Trigger a command once.

int commandTrigger (int commandHandle, int triggerCount)

Trigger a command multiple times.

• int commandStart (int commandHandle)

Start a command. All commandStart must be balanced with a commandEnd.

• int commandEnd (int commandHandle)

End a command. All commandStart must be balanced with a commandEnd.

· void datarefWrite (int handle, long value)

Write an integer DataRef.

· void datarefWrite (int handle, int value)

Write an integer DataRef. Maps to long DataRefs.

void datarefWrite (int handle, long value, int arrayElement)

Write a Integer DataRef to an array element.

void datarefWrite (int handle, int value, int arrayElement)

Write a Integer DataRef to an array element. Maps to long DataRefs.

void datarefWrite (int handle, float value)

Write a float DataRef.

void datarefWrite (int handle, float value, int arrayElement)

Write a float DataRef to an array element.

void requestUpdates (int handle, int rate, float precision)

Request DataRef updates from the plugin.

• void requestUpdates (int handle, int rate, float precision, int arrayElement)

Request DataRef updates from the plugin for an array DataRef.

void setScaling (int handle, int inLow, int inHigh, int outLow, int outHigh)

set scaling factor for a DataRef (offload mapping to the plugin)

int registerDataRef (XPString_t *datarefName)

Register a DataRef and obtain a handle.

• int registerCommand (XPString_t *commandName)

Register a Command and obtain a handle.

float datarefReadFloat ()

Read the received float DataRef.

• long datarefReadInt ()

Read the received integer DataRef.

int datarefReadElement ()

Read the received array element.

int sendDebugMessage (const char *msg)

Send a debug message to the plugin.

int sendSpeakMessage (const char *msg)

Send a speech message to the plugin.

void sendResetRequest (void)

Request a reset from the plugin.

• int xloop ()

Cyclic loop handler, must be called in idle task.

3.1.1 Detailed Description

Core class for the XPLPro Arduino library.

Definition at line 99 of file XPLPro.h.

3.1.2 Constructor & Destructor Documentation

3.1.2.1 XPLPro()

Constructor.

Parameters

device Device to use (should be &Serial)

Definition at line 5 of file XPLPro.cpp.

3.1.3 Member Function Documentation

3.1.3.1 begin()

Register device and set callback functions.

Parameters

devicename	Device name
initFunction	Callback for DataRef and Command registration
stopFunction	Callback for XPlane shutdown or plane change
inboundHandler	Callback for incoming DataRefs

Definition at line 11 of file XPLPro.cpp.

3.1.3.2 commandEnd()

End a command. All commandStart must be balanced with a commandEnd.

Parameters

commandHandle	Handle of the command to start

Returns

0: OK, -1: command was not registered

Definition at line 58 of file XPLPro.cpp.

3.1.3.3 commandStart()

Start a command. All commandStart must be balanced with a commandEnd.

Parameters

ommandHandle Handle of the comma	nd to start
----------------------------------	-------------

Returns

0: OK, -1: command was not registered

Definition at line 48 of file XPLPro.cpp.

3.1.3.4 commandTrigger() [1/2]

Trigger a command once.

Parameters

commandHandle	of the command to trigger
---------------	---------------------------

Returns

0: OK, -1: command was not registered

Definition at line 120 of file XPLPro.h.

3.1.3.5 commandTrigger() [2/2]

Trigger a command multiple times.

Parameters

commandHandle	Handle of the command to trigger
triggerCount	Number of times to trigger the command

Returns

0: OK, -1: command was not registered

Definition at line 37 of file XPLPro.cpp.

3.1.3.6 connectionStatus()

```
int XPLPro::connectionStatus ( )
```

Return connection status.

Returns

True if connection to XPlane established

Definition at line 68 of file XPLPro.cpp.

3.1.3.7 datarefReadElement()

```
int XPLPro::datarefReadElement ( ) [inline]
```

Read the received array element.

Returns

Received array element

Definition at line 207 of file XPLPro.h.

3.1.3.8 datarefReadFloat()

```
float XPLPro::datarefReadFloat ( ) [inline]
```

Read the received float DataRef.

Returns

Received value

Definition at line 199 of file XPLPro.h.

3.1.3.9 datarefReadInt()

```
long XPLPro::datarefReadInt ( ) [inline]
```

Read the received integer DataRef.

Returns

Received value

Definition at line 203 of file XPLPro.h.

3.1.3.10 datarefWrite() [1/6]

Write a float DataRef.

Parameters

handle	Handle of the DataRef to write
value	Value to write to the DataRef

Definition at line 127 of file XPLPro.cpp.

3.1.3.11 datarefWrite() [2/6]

```
void XPLPro::datarefWrite (
                int handle,
                float value,
                int arrayElement )
```

Write a float DataRef to an array element.

Parameters

handle	Handle of the DataRef to write
value	Value to write to the DataRef
arrayElement	Array element to write to

Definition at line 144 of file XPLPro.cpp.

3.1.3.12 datarefWrite() [3/6]

Write an integer DataRef. Maps to long DataRefs.

Parameters

handle	Handle of the DataRef to write
value	Value to write to the DataRef

Definition at line 87 of file XPLPro.cpp.

3.1.3.13 datarefWrite() [4/6]

```
void XPLPro::datarefWrite (
          int handle,
          int value,
          int arrayElement )
```

Write a Integer DataRef to an array element. Maps to long DataRefs.

Parameters

handle	Handle of the DataRef to write
value	Value to write to the DataRef
arrayElement	Array element to write to

Definition at line 97 of file XPLPro.cpp.

3.1.3.14 datarefWrite() [5/6]

Write an integer DataRef.

Parameters

handle	Handle of the DataRef to write
value	Value to write to the DataRef

Definition at line 107 of file XPLPro.cpp.

3.1.3.15 datarefWrite() [6/6]

```
void XPLPro::datarefWrite (
          int handle,
          long value,
          int arrayElement )
```

Write a Integer DataRef to an array element.

Parameters

handle	Handle of the DataRef to write
value	Value to write to the DataRef
arrayElement	Array element to write to

Definition at line 117 of file XPLPro.cpp.

3.1.3.16 registerCommand()

Register a Command and obtain a handle.

Parameters

commandName	Name of the Command (or abbreviation)

Returns

Assigned handle for the Command, -1 if Command was not found

Definition at line 459 of file XPLPro.cpp.

3.1.3.17 registerDataRef()

Register a DataRef and obtain a handle.

Parameters

datarefName	Name of the DataRef (or abbreviation)
-------------	---------------------------------------

Returns

Assigned handle for the DataRef, -1 if DataRef was not found

Definition at line 434 of file XPLPro.cpp.

3.1.3.18 requestUpdates() [1/2]

Request DataRef updates from the plugin.

Parameters

handle	Handle of the DataRef to subscribe to
rate	Maximum rate for updates to reduce traffic
precision	Floating point precision

Definition at line 476 of file XPLPro.cpp.

3.1.3.19 requestUpdates() [2/2]

```
void XPLPro::requestUpdates (
                int handle,
                int rate,
                float precision,
                int arrayElement )
```

Request DataRef updates from the plugin for an array DataRef.

Parameters

handle	Handle of the DataRef to subscribe to
rate	Maximum rate for updates to reduce traffic
precision	Floating point precision
arrayElement	Array element to subscribe to

Definition at line 490 of file XPLPro.cpp.

3.1.3.20 sendDebugMessage()

Send a debug message to the plugin.

Parameters

msg Message to show as debug string

Returns

Definition at line 73 of file XPLPro.cpp.

3.1.3.21 sendResetRequest()

Request a reset from the plugin.

Definition at line 171 of file XPLPro.cpp.

3.1.3.22 sendSpeakMessage()

Send a speech message to the plugin.

Parameters

msg Message to speak

Returns

Definition at line 79 of file XPLPro.cpp.

3.1.3.23 setScaling()

```
void XPLPro::setScaling (
    int handle,
    int inLow,
    int inHigh,
    int outLow,
    int outHigh)
```

set scaling factor for a DataRef (offload mapping to the plugin)

Definition at line 505 of file XPLPro.cpp.

3.1.3.24 xloop()

Cyclic loop handler, must be called in idle task.

Returns

Connection status

Definition at line 22 of file XPLPro.cpp.

The documentation for this class was generated from the following files:

- XPLPro.h
- XPLPro.cpp

Chapter 4

File Documentation

4.1 Direct inputs/main.cpp

```
00001 #include <Arduino.h>
00002 #include <XPLPro.h>
00003
00004 // The XPLDirect library is automatically installed by PlatformIO with XPLDevices 00005 // Optional defines for XPLDirect can be set in platformio.ini
00006 // This sample contains all the important defines. Modify or remove as needed
00008 // A simple Pushbutton on Arduino pin 2
00009 Button btnStart(2);
00010
00011 // An Encoder with push functionality. 3&4 are the encoder pins, 5 the push pin. 00012 // configured for an Encoder with 4 counts per mechanical notch, which is the standard
00013 Encoder encHeading(3, 4, 5, enc4Pulse);
00015 // A simple On/Off switch on pin 6
00016 Switch swStrobe(6);
00017
00018 // A handle for a DataRef
00019 int drefStrobe;
00021 void xpInit()
00022 {
         // Register Command for the Button
btnStart.setCommand(F("sim/starters/engage_starter_1"));
00023
00024
00025
00026
         // Register Commands for Encoder Up/Down/Push function.
00027
         encHeading.setCommand(F("sim/autopilot/heading_up"),
                                   F("sim/autopilot/heading_down"),
00028
00029
                                   F("sim/autopilot/heading_sync"));
00030
00031
         // Register Commands for Switch On and Off transitions. Commands are sent when Switch is moved
00032
         swStrobe.setCommand(F("sim/lights/strobe_lights_on"),
00033
                                F("sim/lights/strobe_lights_off"));
00034
00035
         // Register a DataRef for the strobe light. Subscribe to updates from XP, 100ms minimum Cycle time,
no divider
00036    drefStrobe = XP.registerDataRef(F("sim/cockpit/electrical/strobe_lights_on"));
00037    XP.requestUpdates(drefStrobe, 100, 0);
00038 }
00039
00040 void xpStop()
00041 {
00042
         // nothing to do on unload
00043 }
00045 void xpUpdate(int handle)
00046 {
00047
         if (handle == drefStrobe)
        { // Show the status of the Strobe on the internal LED
digitalWrite(LED_BUILTIN, (XP.datarefReadInt() > 0));
00048
00049
00050
00051 }
00052
00053 // Arduino setup function, called once
00054 void setup() {
       // setup interface
Serial.begin(XPLDIRECT_BAUDRATE);
00055
00057 XP.begin("Sample", &xpInit(), &xpStop(), &xpUpdate());
```

```
00058 }
00059
00060 // Arduino loop function, called cyclic
00061 void loop() {
       // Handle XPlane interface
00062
00063
       XP.xloop();
00065
        // handle all devices and automatically process commands
00066
       btnStart.handleXP();
00067
        encHeading.handleXP();
00068
       swStrobe.handleXP();
00069 }
```

4.2 MUX inputs/main.cpp

```
00001 #include <Arduino.h>
00002 #include <XPLPro.h>
00003
00004 // The XPLDirect library is automatically installed by PlatformIO with XPLDevices
00005 // Optional defines for XPLDirect can be set in platformio.ini
00006 // This sample contains all the important defines. Modify or remove as needed
00008 // This sample shows how to use 74HC4067 Multiplexers for the inputs as commonly used by SimVim
00009
00010 // A simple Pushbutton on MUX0 pin 0
00011 Button btnStart(0, 0);
00013 // An Encoder with push functionality. MUX1 pin 8\&9 are the encoder pins, 10 the push pin.
00014 // configured for an Encoder with 4 counts per mechanical notch, which is the standard
00015 Encoder encHeading(1, 8, 9, 10, enc4Pulse);
00016
00017 // A simple On/Off switch on MUXO, pin 15
00018 Switch swStrobe(0, 15);
00019
00020 // A handle for a DataRef
00021 int drefStrobe;
00022
00023 void xpInit()
00024 {
00025
        // Register Command for the Button
00026
        btnStart.setCommand(F("sim/starters/engage_starter_1"));
00027
        // Register Commands for Encoder Up/Down/Push function.
00028
       encHeading.setCommand(F("sim/autopilot/heading_up"),
00029
                               F("sim/autopilot/heading_down"
00031
                               F("sim/autopilot/heading_sync"));
00032
00033
       // Register a DataRef for the strobe light. Subscribe to updates from XP, 100ms minimum Cycle time,
     no divider
00034 drefStrobe = XP.registerDataRef(F("sim/cockpit/electrical/strobe_lights_on"));
00035
       XP.requestUpdates(drefStrobe, 100, 0);
00036 }
00037
00038 void xpStop()
00039 {
00040
        // nothing to do on unload
00041 }
00042
00043 void xpUpdate(int handle)
00044 {
00045
        if (handle == drefStrobe)
       \{ // Show the status of the Strobe on the internal LED
00046
00047
          digitalWrite(LED_BUILTIN, (XP.datarefReadInt() > 0));
00049 }
00050
00051 // Arduino setup function, called once
00052 void setup() {
00053 // setup interface
        Serial.begin(XPLDIRECT_BAUDRATE);
00054
       XP.begin("Sample", &xpInit(), &xpStop(), &xpUpdate());
00056
00057
        // Connect MUX adress pins to Pin 22-25 (SimVim Pins)
00058
        DigitalIn.setMux(22, 23, 24, 25);
00059
        // Logical MUX0 on Pin 38
00060
       DigitalIn.addMux(38);
00061
           Logical MUX1 on Pin 39
00062
      DigitalIn.addMux(39);
00063 }
00064
00065 // Arduino loop function, called cyclic
00066 void loop() {
       // Handle XPlane interface
```

4.3 XPLPro.cpp 19

```
00068    XP.xloop();
00069
00070    // handle all devices and automatically process commandsin background
00071    btnStart.handleXP();
00072    encHeading.handleXP();
00073    swStrobe.handleXP();
```

4.3 XPLPro.cpp

```
00001 // XPLPro.cpp 00002 // Created by Curiosity Workshop, Michael Gerlicher, 2023.
00003 #include "XPLPro.h"
00005 XPLPro::XPLPro(Stream *device)
00006 {
        _streamPtr = device;
00007
       _streamPtr->setTimeout(XPL_RX_TIMEOUT);
80000
00009 }
00010
00011 void XPLPro::begin(const char *devicename, void (*initFunction)(void), void (*stopFunction)(void),
      void (*inboundHandler)(int))
00012 {
        _deviceName = (char *)devicename;
00013
        _connectionStatus = 0;
00014
        _receiveBuffer[0] = 0;
00015
        _registerFlag = 0;
00016
        _xplInitFunction = initFunction;
00017
00018
        _xplStopFunction = stopFunction;
00019
       _xplInboundHandler = inboundHandler;
00020 }
00021
00022 int XPLPro::xloop(void)
00023 {
        // handle incoming serial data
00024
00025
        _processSerial();
        // when device is registered, perform handle registrations if (_registerFlag)
00026
00027
00028
        {
00029
         _xplInitFunction();
00030
         _registerFlag = 0;
00031
00032
       // return status of connection
00033
       return _connectionStatus;
00034 }
00035
00036 // TODO: is a return value necessary? These could also be void like for the datarefs
00037 int XPLPro::commandTrigger(int commandHandle, int triggerCount)
00038 {
00039
        if (commandHandle < 0)
00040
       {
00041
          return XPL_HANDLE_INVALID;
00042
00043 sprintf(_sendBuffer, "%c%c,%i,%i%c", XPL_PACKETHEADER, XPLCMD_COMMANDTRIGGER, commandHandle,
     triggerCount, XPL_PACKETTRAILER);
00044
       _transmitPacket();
00045
        return 0;
00046 }
00047
00048 int XPLPro::commandStart(int commandHandle)
00049 {
00050
        if (commandHandle < 0)
00051
       {
00052
         return XPL_HANDLE_INVALID;
00053
00054
       _sendPacketVoid(XPLCMD_COMMANDSTART, commandHandle);
00055
00056 }
00057
00058 int XPLPro::commandEnd(int commandHandle)
00059 {
00060
        if (commandHandle < 0)</pre>
00061
          return XPL_HANDLE_INVALID;
00062
00063
        _sendPacketVoid(XPLCMD_COMMANDEND, commandHandle);
00064
00065
        return 0;
00066 }
00067
00068 int XPLPro::connectionStatus()
00069 {
00070
        return _connectionStatus;
00071 }
```

```
00073 int XPLPro::sendDebugMessage(const char *msg)
00074 {
       _sendPacketString(XPLCMD_PRINTDEBUG, msg);
00075
00076
        return 1;
00077 }
00079 int XPLPro::sendSpeakMessage(const char *msg)
00080 {
00081
         _sendPacketString(XPLCMD_SPEAK, msg);
00082
        return 1;
00083 }
00084
00085 // these could be done better:
00086
00087 void XPLPro::datarefWrite(int handle, int value)
00088 {
00089
        if (handle < 0)
00090
00091
          return;
00092
00093
        sprintf(_sendBuffer, "%c%c,%i,%i%c", XPL_PACKETHEADER, XPLCMD_DATAREFUPDATEINT, handle, value,
      XPL_PACKETTRAILER);
       _transmitPacket();
00094
00095 }
00097 void XPLPro::datarefWrite(int handle, int value, int arrayElement)
00098 {
00099
        if (handle < 0)</pre>
00100
        {
00101
          return:
00102
        sprintf(_sendBuffer, "%c%c,%i,%i,%i%c", XPL_PACKETHEADER, XPLCMD_DATAREFUPDATEINTARRAY, handle,
00103
      value, arrayElement, XPL_PACKETTRAILER);
00104 _transmitPacket();
00105 }
00106
00107 void XPLPro::datarefWrite(int handle, long value)
00108 {
00109
        if (handle < 0)</pre>
00110
        {
00111
          return;
00112
        sprintf(_sendBuffer, "%c%c,%i,%ld%c", XPL_PACKETHEADER, XPLCMD_DATAREFUPDATEINT, handle, value,
00113
     XPL_PACKETTRAILER);
       _transmitPacket();
00114
00115 }
00116
00117 void XPLPro::datarefWrite(int handle, long value, int arrayElement)
00118 {
00119
        if (handle < 0)</pre>
00120
        {
00121
          return;
00122
        sprintf(_sendBuffer, "%c%c,%i,%ld,%i%c", XPL_PACKETHEADER, XPLCMD_DATAREFUPDATEINTARRAY, handle,
00123
     value, arrayElement, XPL_PACKETTRAILER);
00124
       _transmitPacket();
00125 }
00126
00127 void XPLPro::datarefWrite(int handle, float value)
00128 {
00129
        if (handle < 0)</pre>
00130
        {
00131
00132
00133
        char tBuf[20]; // todo: rewrite to eliminate this buffer. Write directly to _sendBuffer
00134
        dtostrf(value, 0, XPL_FLOATPRECISION, tBuf);
sprintf(_sendBuffer, "%c%c,%i,%s%c",
00135
                XPL_PACKETHEADER,
00136
00137
                XPLCMD_DATAREFUPDATEFLOAT,
00138
                handle,
00139
                tBuf,
00140
                XPL_PACKETTRAILER);
        _transmitPacket();
00141
00142 }
00144 void XPLPro::datarefWrite(int handle, float value, int arrayElement)
00145 {
00146
        if (handle < 0)
00147
        {
00148
          return;
00149
00150
        char tBuf[20]; // todo: rewrite to eliminate this buffer. Write directly to _sendBuffer
00151
        dtostrf(value, 0, XPL_FLOATPRECISION, tBuf);
00152
        sprintf(_sendBuffer, "%c%c,%i,%s,%i%c",
                XPL PACKETHEADER.
00153
00154
                XPLCMD_DATAREFUPDATEFLOATARRAY,
```

4.3 XPLPro.cpp 21

```
00155
                handle,
00156
                tBuf,
00157
                arrayElement,
00158
                XPL_PACKETTRAILER);
        _transmitPacket();
00159
00160 }
00161
00162 void XPLPro::_sendname()
00163 {
        // register device on request only when we have a valid name if (_deviceName !=\mbox{NULL})
00164
00165
00166
       {
          _sendPacketString(XPLRESPONSE_NAME, _deviceName);
00167
00168
00169 }
00170
00171 void XPLPro::sendResetRequest()
00172 {
       // request a reset only when we have a valid name
        if (_deviceName != NULL)
00175
         _sendPacketVoid(XPLCMD_RESET, 0);
00176
00177
       }
00178 }
00179
00180 void XPLPro::_processSerial()
00181 {
00182
        // read until package header found or buffer empty
00183
        while (_streamPtr->available() && _receiveBuffer[0] != XPL_PACKETHEADER)
00184
00185
          _receiveBuffer[0] = (char)_streamPtr->read();
00186
00187
        ^{\prime}// return when buffer empty and header not found
00188
        if (_receiveBuffer[0] != XPL_PACKETHEADER)
00189
00190
          return;
00191
00192
       // read rest of package until trailer
00193
        _receiveBufferBytesReceived = _streamPtr->readBytesUntil(XPL_PACKETTRAILER, (char
      *)&_receiveBuffer[1], XPLMAX_PACKETSIZE_RECEIVE - 1);
00194
       // if no further chars available, delete package
00195
        if (_receiveBufferBytesReceived == 0)
00196
        {
         _receiveBuffer[0] = 0;
00197
00198
         return;
00199
00200
       // add package trailer and zero byte to frame
        _receiveBuffer[++_receiveBufferBytesReceived] = XPL_PACKETTRAILER;
00201
00202
        _receiveBuffer[++_receiveBufferBytesReceived] = 0; // old habits die hard.
00203
        // at this point we should have a valid frame
       _processPacket();
00204
00205 }
00206
00207 void XPLPro::_processPacket()
00208 {
00209
        int tHandle;
       // check whether we have a valid frame
00210
00211
        if (_receiveBuffer[0] != XPL_PACKETHEADER)
00212
00213
          return:
00214
        // branch on receiverd command
00215
00216
        switch (_receiveBuffer[1])
00217
00218
        // plane unloaded or XP exiting
00219
        case XPL_EXITING:
00220
        _connectionStatus = false;
          _xplStopFunction();
00221
00222
          break;
00224
        // register device
00225
        case XPLCMD_SENDNAME:
         _sendname();
00226
         _connectionStatus = true; // not considered active till you know my name
00227
         _registerFlag = 0;
break;
00228
00229
00230
00231
        \ensuremath{//} plugin is ready for registrations.
00232
        case XPLCMD_SENDREQUEST:
          _registerFlag = 1; // use a flag to signal registration so recursion doesn't occur
00233
00234
          break:
00235
00236
        // get handle from response to registered dataref
00237
        case XPLRESPONSE_DATAREF:
00238
          _parseInt(&_handleAssignment, _receiveBuffer, 2);
00239
00240
```

```
// get handle from response to registered command
00242
        case XPLRESPONSE_COMMAND:
        _parseInt(&_handleAssignment, _receiveBuffer, 2);
00243
00244
         break;
00245
00246
        // int dataref received
        case XPLCMD_DATAREFUPDATEINT:
00248
         _parseInt(&tHandle, _receiveBuffer, 2);
00249
          _parseInt(&_readValueLong, _receiveBuffer, 3);
         _readValueFloat = 0;
_readValueElement = 0;
00250
00251
          _xplInboundHandler(tHandle);
00252
00253
          break;
00254
00255
        // int array dataref received
00256
        case XPLCMD_DATAREFUPDATEINTARRAY:
00257
         _parseInt(&tHandle, _receiveBuffer, 2);
          __rarseInt(&_readValueLong, __receiveBuffer, 3);
__parseInt(&_readValueElement, __receiveBuffer, 4);
00258
00259
          _readValueFloat = 0;
00260
          _xplInboundHandler(tHandle);
00261
00262
          break;
00263
00264
        // float dataref received
00265
        case XPLCMD_DATAREFUPDATEFLOAT:
00266
         _parseInt(&tHandle, _receiveBuffer, 2);
00267
          _parseFloat(&_readValueFloat, _receiveBuffer, 3);
         _readValueLong = 0;
00268
         _readValueElement = 0;
00269
          _xplInboundHandler(tHandle);
00270
00271
          break:
00272
00273
        // float array dataref received
00274
        case XPLCMD_DATAREFUPDATEFLOATARRAY:
00275
         _parseInt(&tHandle, _receiveBuffer, 2);
00276
          _parseFloat(&_readValueFloat, _receiveBuffer, 3);
00277
         _parseInt(&_readValueElement, _receiveBuffer, 4);
         _readValueLong = 0;
00278
00279
          _xplInboundHandler(tHandle);
00280
00281
       // obsolete?
00282
00283
       case XPLREQUEST REFRESH:
00284
         break;
00285
00286
        default:
00287
         break;
00288
        // empty receive buffer
00289
        _receiveBuffer[0] = 0;
00290
00291 }
00292
00293 void XPLPro::_sendPacketVoid(int command, int handle) // just a command with a handle
00294 {
00295
        // check for valid handle
00296
        if (handle < 0)</pre>
00297
00298
          return:
00299
        sprintf(_sendBuffer, "%c%c,%i%c", XPL_PACKETHEADER, command, handle, XPL_PACKETTRAILER);
00300
        _transmitPacket();
00301
00302 }
00303
00304 void XPLPro::_sendPacketString(int command, const char *str) // for a string
00305 {
00306
        sprintf(_sendBuffer, "%c%c,\"%s\"%c", XPL_PACKETHEADER, command, str, XPL_PACKETTRAILER);
00307
        _transmitPacket();
00308 }
00309
00310 void XPLPro::_transmitPacket(void)
00311 {
00312
        _streamPtr->write(_sendBuffer);
00313
        if (strlen(_sendBuffer) == 64)
00314
       {
          // apparently a bug in arduino with some boards when we transmit exactly 64 bytes. That took a
00315
      while to track down..
00316
         _streamPtr->print(" ");
00317
00318 }
00319
00320 int XPLPro::_parseString(char *outBuffer, char *inBuffer, int parameter, int maxSize)
00321 {
00322
        int cBeg;
00323
        int pos = 0;
00324
       int len;
00325
00326
       for (int i = 1; i < parameter; i++)
```

4.3 XPLPro.cpp 23

```
00328
          while (inBuffer[pos] != ',' && inBuffer[pos] != 0)
00329
00330
            pos++;
00331
00332
          pos++;
00333
00334
00335
        while (inBuffer[pos] != '\"' && inBuffer[pos] != 0)
00336
00337
         pos++;
00338
00339
        cBeg = ++pos;
00340
00341
        while (inBuffer[pos] != '\"' && inBuffer[pos] != 0)
00342
00343
          pos++;
00344
00345
        len = pos - cBeg;
00346
        if (len > maxSize)
00347
00348
          len = maxSize;
00349
00350
        strncpy(outBuffer, (char *)&inBuffer[cBeg], len);
        outBuffer[len] = 0;

// fprintf(errlog, "_parseString, pos: %i, cBeg: %i, deviceName: %s\n", pos, cBeg, target);
00351
00352
00353
00354 }
00355
00356 int XPLPro::_parseInt(int *outTarget, char *inBuffer, int parameter)
00357 {
00358
        int cBeq;
00359
        int pos = 0;
00360
        \ensuremath{//} search for the selected parameter
00361
        for (int i = 1; i < parameter; i++)</pre>
00362
00363
          while (inBuffer[pos] != ',' && inBuffer[pos] != 0)
00364
00365
           pos++;
00366
00367
          pos++;
00368
        // parameter starts here
00369
00370
        cBeq = pos;
00371
        // search for end of parameter
00372
        while (inBuffer[pos] != ',' && inBuffer[pos] != 0 && inBuffer[pos] != XPL_PACKETTRAILER)
00373
00374
          pos++;
00375
00376
        // temporarily make parameter null terminated
        char holdChar = inBuffer[pos];
inBuffer[pos] = 0;
00377
00378
00379
        // get integer value from string
00380
        *outTarget = atoi((char *)&inBuffer[cBeg]);
00381
        // restore buffer
00382
        inBuffer[pos] = holdChar;
00383
        return 0;
00384 }
00385
00386 int XPLPro::_parseInt(long *outTarget, char *inBuffer, int parameter)
00387 {
        int cBeg;
00388
00389
        int pos = 0;
00390
        for (int i = 1; i < parameter; i++)</pre>
00391
00392
          while (inBuffer[pos] != ',' && inBuffer[pos] != 0)
00393
00394
            pos++;
00395
00396
          pos++;
00397
00398
        cBeg = pos;
        while (inBuffer[pos] != ',' && inBuffer[pos] != 0 && inBuffer[pos] != XPL_PACKETTRAILER)
00399
00400
00401
          pos++;
00402
00403
        char holdChar = inBuffer[pos];
00404
        inBuffer[pos] = 0;
00405
        *outTarget = atoi((char *)&inBuffer[cBeg]);
00406
        inBuffer[pos] = holdChar;
00407
        return 0;
00408 }
00409
00410 int XPLPro::_parseFloat(float *outTarget, char *inBuffer, int parameter)
00411 {
00412
        int cBeg;
00413
       int pos = 0;
```

```
for (int i = 1; i < parameter; i++)</pre>
00415
          while (inBuffer[pos] != ',' && inBuffer[pos] != 0)
00416
00417
00418
            pos++;
00419
00420
          pos++;
00421
00422
        while (inBuffer[pos] != ',' && inBuffer[pos] != 0 && inBuffer[pos] != XPL_PACKETTRAILER)
00423
00424
00425
          pos++;
00426
00427
        char holdChar = inBuffer[pos];
00428
        inBuffer[pos] = 0;
00429
        *outTarget = atof((char *)&inBuffer[cBeg]);
00430
        inBuffer[pos] = holdChar;
00431
        return 0;
00432 }
00433
00434 int XPLPro::registerDataRef(XPString_t *datarefName)
00435 {
00436
        long int startTime;
00437
00438
        // registration only allowed in callback (TODO: is this limitation really necessary?)
00439
        if (!_registerFlag)
00440
00441
          return XPL_HANDLE_INVALID;
00442
00443 #if XPL USE PROGMEM
00444 sprintf(_sendBuffer, "%c%c,\"%S\"%c", XPL_PACKETHEADER, XPLREQUEST_REGISTERDATAREF, (wchar_t
       *) datarefName, XPL_PACKETTRAILER);
00445 #else
00446
        sprintf(_sendBuffer, "%c%c,\"%s\"%c", XPL_PACKETHEADER, XPLREQUEST_REGISTERDATAREF, (char
      *)datarefName, XPL_PACKETTRAILER);
00447 #endif
00448
        _transmitPacket();
00449
00450
         _handleAssignment = XPL_HANDLE_INVALID;
00451
        startTime = millis(); // for timeout function
00452
00453
       while (millis() - startTime < XPL_RESPONSE_TIMEOUT && _handleAssignment < 0)</pre>
          _processSerial();
00454
00455
00456
        return _handleAssignment;
00457 }
00458
00459 int XPLPro::registerCommand(XPString_t *commandName)
00460 {
00461
        long int startTime = millis(); // for timeout function
00462 #if XPL_USE_PROGMEM
        sprintf(_sendBuffer, "%c%c,\"%S\"%c", XPL_PACKETHEADER, XPLREQUEST_REGISTERCOMMAND, (wchar_t
      *)commandName, XPL_PACKETTRAILER);
00464 #else
00465 sprintf(_sendBuffer, "%c%c,\"%s\"%c", XPL_PACKETHEADER, XPLREQUEST_REGISTERCOMMAND, (char
       *) commandName, XPL_PACKETTRAILER);
00466 #endif
00467
00468
        _handleAssignment = XPL_HANDLE_INVALID;
00469
        while (millis() - startTime < XPL_RESPONSE_TIMEOUT && _handleAssignment < 0)</pre>
00470
        {
          _processSerial();
00471
00472
00473
        return _handleAssignment;
00474 }
00475
00476 void XPLPro::requestUpdates(int handle, int rate, float precision)
00477 {
00478
        char tBuf[20]; // todo: rewrite to eliminate this buffer. Write directly to _sendBuffer?
        dtostrf(precision, 0, XPL_FLOATPRECISION, tBuf); sprintf(_sendBuffer, "%c%c,%i,%i,%s%c",
00480
00481
                 XPL PACKETHEADER,
00482
                 XPLREQUEST_UPDATES,
00483
                 handle,
00484
                 rate,
00485
                 tBuf.
00486
                 XPL_PACKETTRAILER);
00487
        _transmitPacket();
00488 }
00489
00490 void XPLPro::requestUpdates(int handle, int rate, float precision, int element)
00491 {
00492
        char tBuf[20]; // todo: rewrite to eliminate this buffer. Write directly to _sendBuffer?
        dtostrf(precision, 0, XPL_FLOATPRECISION, tBuf);
sprintf(_sendBuffer, "%c%c,%i,%i,%s,%i%c",
00493
00494
                 XPL PACKETHEADER.
00495
00496
                 XPLREOUEST UPDATESARRAY.
```

4.4 XPLPro.h 25

```
00497
                 handle,
00498
                 rate,
00499
                 tBuf,
00500
                 element,
00501
                 XPL PACKETTRAILER):
00502
        _transmitPacket();
00503 }
00504
00505 void XPLPro::setScaling(int handle, int inLow, int inHigh, int outLow, int outHigh)
00506 {
        sprintf(_sendBuffer, "%c%c,%i,%i,%i,%i,%i,%i%c",
00507
                 XPL_PACKETHEADER,
00508
00509
                 XPLREQUEST_SCALING,
00510
                 handle,
00511
                 inLow,
00512
                 inHigh,
00513
                 out Low,
00514
                 out High,
                 XPL_PACKETTRAILER);
UU516 _transmitPacket();
00517 }
```

4.4 XPLPro.h

```
00001 //
            XPLPro.h - Library for serial interface to Xplane SDK.
            Created by Curiosity Workshop, Michael Gerlicher, 2020-2023
00002 //
            See readme.txt file for information on updates.
00004 // To report problems, download updates and examples, suggest enhancements or get technical support,
      please visit:
00005 //
              discord: https://discord.gg/gzXetjEST4
00006 //
               patreon: www.patreon.com/curiosityworkshop
00007
00008 #ifndef XPLPro_h
00009 #define XPLPro_h
00010
00011 #include <Arduino.h>
00012
00014 // Parameters that can be overwritten by command line defines
00016
00017 // Decimals of precision for floating point datarefs. More increases dataflow (default 4)
00018 #ifndef XPL_FLOATPRECISION
00019 #define XPL_FLOATPRECISION 4
00020 #endif
00021
00022 // Timeout after sending a registration request, how long will we wait for the response.
00023 // This is giant because sometimes xplane says the plane is loaded then does other stuff for a while.
      (default 90000 ms)
00024 #ifndef XPL_RESPONSE_TIMEOUT
00025 #define XPL_RESPONSE_TIMEOUT 90000
00026 #endif
00027
00028 \!\!\!\!// For boards with limited memory that can use PROGMEM to store strings.
00029 // You will need to wrap your dataref names with F() macro ie:
00030 // Xinterface.registerDataref(F("laminar/B738/annunciator/drive2"), XPL_READ, 100, 0, &drive2);
00031 // Disable for boards that have issues compiling: errors with strncmp_PF for instance. 00032 #ifndef XPL_USE_PROGMEM 00033 #ifdef __AVR_ARCH__
00034 // flash strings are default on on AVR architecture
00035 #define XPL_USE_PROGMEM 1
00036 #else
00037 // and off otherwise
00038 #define XPL_USE_PROGMEM 0
00039 #endif
00040 #endif
00041
00042 // Package buffer size for send and receive buffer each.
00043 // If you need a few extra bytes of RAM it could be reduced, but it needs to 00044 // be as long as the longest dataref name + 10. If you are using datarefs 00045 // that transfer strings it needs to be big enough for those too. (default 200)
00046 #ifndef XPLMAX_PACKETSIZE_TRANSMIT
00047 #define XPLMAX_PACKETSIZE_TRANSMIT 200
00048 #endif
00049
00050 #ifndef XPLMAX PACKETSIZE RECEIVE
00051 #define XPLMAX_PACKETSIZE_RECEIVE 200
00052 #endif
00053
00055 // All other defines in this header must not be modified
00057
00058 // define whether flash strings will be used
00059 #if XPL_USE_PROGMEM
00060 // use Flash for strings, requires F() macro for strings in all registration calls
00061 typedef const __FlashStringHelper XPString_t;
```

```
00062 #else
00063 typedef const char XPString t;
00064 #endif
00065
00066 // Parameters around the interface
00067 #define XPL_BAUDRATE 115200 // Baudrate needed to match plugin 00068 #define XPL_RX_TIMEOUT 500 // Timeout for reception of one frame
00069 #define XPL_PACKETHEADER '[' // Frame start character 00070 #define XPL_PACKETTRAILER ']' // Frame end character
00071 #define XPL_HANDLE_INVALID -1 // invalid handle
00072
00073 // Items in caps generally come from XPlane. Items in lower case are generally sent from the arduino.
00074 #define XPLCMD_SENDNAME 'N
                                                    // plugin request name from arduino
                                                    // Arduino responds with device name as initialized in the
00075 #define XPLRESPONSE_NAME 'n'
     "begin" function
00076 #define XPLCMD_SENDREQUEST 'Q'
                                                    // plugin sends this when it is ready to register bindings
00077 #define XPLREQUEST_REGISTERDATAREF 'b'
                                                    // Register a dataref
00078 #define XPLREQUEST_REGISTERCOMMAND 'm'
                                                    // Register a command
00079 #define XPLRESPONSE_DATAREF 'D'
                                                    // Plugin responds with handle to dataref or - value if not
      found. dataref handle, dataref name
00080 #define XPLRESPONSE_COMMAND 'C'
                                                    // Plugin responds with handle to command or - value if not
     found. command handle, command name
00081 #define XPLCMD_PRINTDEBUG 'g' 00082 #define XPLCMD_SPEAK 's'
                                                    // Plugin logs string sent from arduino
                                                    // plugin speaks string through xplane speech
// the plugin will call this once xplane is loaded in order
00083 #define XPLREQUEST_REFRESH 'd'
      to get fresh updates from arduino handles that write
00084 #define XPLREQUEST_UPDATES 'r'
                                                    // arduino is asking the plugin to update the specified
      dataref with rate and divider parameters
                                                    \ensuremath{//} arduino is asking the plugin to update the specified
00085 #define XPLREQUEST_UPDATESARRAY 't'
      array dataref with rate and divider parameters
00086 #define XPLREQUEST_SCALING 'u'
                                                    // arduino requests the plugin apply scaling to the dataref
      values
00087 #define XPLCMD_RESET 'z'
                                                    // Request a reset and reregistration from the plugin
00088 #define XPLCMD_DATAREFUPDATEINT '1'
                                                   // Int DataRef update
                                                   // Float DataRef update
00089 #define XPLCMD_DATAREFUPDATEFLOAT '2'
                                                    // Int array DataRef update
00090 #define XPLCMD_DATAREFUPDATEINTARRAY '3'
00091 #define XPLCMD_DATAREFUPDATEFLOATARRAY '4' // Float array DataRef Update
00092 #define XPLCMD_DATAREFUPDATESTRING '9'
                                                    // String DataRef update
00093 #define XPLCMD_COMMANDTRIGGER 'k'
                                                    // Trigger command n times
00094 #define XPLCMD_COMMANDSTART 'i'
                                                    // Begin command (Button pressed)
00095 #define XPLCMD_COMMANDEND 'j'
                                                    // End command (Button released)
                                                    // XPlane sends this to the arduino device during normal
00096 #define XPL_EXITING 'X'
     shutdown of XPlane. It may not happen if xplane crashes.
00099 class XPLPro
00100 {
00101 public:
00104
          XPLPro(Stream *device);
00105
          void begin (const char *devicename, void (*initFunction) (void), void (*stopFunction) (void), void
00111
      (*inboundHandler)(int));
00112
00115
          int connectionStatus();
00116
          int commandTrigger(int commandHandle) { return commandTrigger(commandHandle, 1); };
00120
00121
00126
          int commandTrigger(int commandHandle, int triggerCount);
00127
00131
          int commandStart(int commandHandle);
00132
00136
          int commandEnd(int commandHandle);
00137
00141
          void datarefWrite(int handle, long value);
00142
00146
          void datarefWrite(int handle, int value);
00147
00152
          void datarefWrite(int handle, long value, int arrayElement);
00153
00158
          void datarefWrite(int handle, int value, int arrayElement);
00159
00163
          void datarefWrite(int handle, float value);
00164
00169
          void datarefWrite(int handle, float value, int arrayElement);
00170
00175
          void requestUpdates(int handle, int rate, float precision);
00176
00182
          void requestUpdates(int handle, int rate, float precision, int arrayElement);
00183
00185
          void setScaling (int handle, int inLow, int inHigh, int outLow, int outHigh);
00186
00190
          int registerDataRef(XPString t *datarefName);
00191
00195
          int registerCommand(XPString t *commandName);
00196
00199
          float datarefReadFloat() { return _readValueFloat; }
00200
          long datarefReadInt() { return readValueLong; }
00203
```

4.4 XPLPro.h 27

```
00204
00207
         int datarefReadElement() { return _readValueElement; }
00208
00212
         int sendDebugMessage(const char *msg);
00213
00217
         int sendSpeakMessage(const char *msg);
00218
00220
         void sendResetRequest(void);
00221
00224
         int xloop();
00225
00226 private:
00227
         void _processSerial();
00228
         void _processPacket();
00229
         void _transmitPacket();
00230
         void _sendname();
         00231
00232
00233
00234
         int _parseInt(long *outTarget, char *inBuffer, int parameter);
         int _parseFloat(float *outTarget, char *inBuffer, int parameter);
int _parseString(char *outBuffer, char *inBuffer, int parameter, int maxSize);
00235
00236
00237
         Stream *_streamPtr;
const char *_deviceName;
00238
00239
00240
         byte _registerFlag;
00241
         byte _connectionStatus;
00242
         char _sendBuffer[XPLMAX_PACKETSIZE_TRANSMIT];
00243
         char _receiveBuffer[XPLMAX_PACKETSIZE_RECEIVE];
00244
00245
         int _receiveBufferBytesReceived;
00246
00247
         receive binding requests
         void (*_xplStopFunction)(void); // this function will be called with the plugin receives message
00248
     or detects xplane flight model inactive
00249
        void (*_xplInboundHandler)(int); // this function will be called when the plugin sends dataref
00250
00251
         int _handleAssignment;
00252
         long _readValueLong;
00253
         float _readValueFloat;
00254
         int _readValueElement;
00255 };
```

Index

begin XPLPro, 7
commandEnd XPLPro, 7
commandStart XPLPro, 7
commandTrigger XPLPro, 8
connectionStatus XPLPro, 9
datarefReadElement
XPLPro, 9 datarefReadFloat
XPLPro, 9 datarefReadInt
XPLPro, 9 datarefWrite XPLPro, 10–12
main.cpp, 17, 18
registerCommand
XPLPro, 12 registerDataRef
XPLPro, 12
requestUpdates XPLPro, 13
sendDebugMessage XPLPro, 14
sendResetRequest XPLPro, 14
sendSpeakMessage XPLPro, 14
setScaling XPLPro, 14
xloop XPLPro, 15
XPLPro, 5
begin, 7
commandEnd, 7
commandStart, 7 commandTrigger, 8
connectionStatus, 9
datarefReadElement, 9
datarefReadFloat, 9
datarefReadInt, 9
datarefWrite, 10–12

```
registerCommand, 12
registerDataRef, 12
requestUpdates, 13
sendDebugMessage, 14
sendResetRequest, 14
sendSpeakMessage, 14
setScaling, 14
xloop, 15
XPLPro, 6
```